
APRS


Pinpoint is a Windows program for APRS.




Last update: 2020/01/01 07:48

Configuration

To use with Signalink, see the Signalink How-to.



Once the radio, the Signalink, and the Soundmodem are configured, start PinPoint and change these settings:



Note:

• Network Kiss Port (8100) in the PinPoint settings needed to be changed to match the SoundModem settings.

8100

• Also, the Serial TNC Settings don't matter since they are not being used by Network Kiss.

Port

SSID

You'll sometimes see a dash number after the callsign, this is called an SSID and they have different meaning depending on whether you're on APRS or Winlink. See the SSID How-To for more info.